

World MoveIt! Day 2019 China Developer Workshop

Hands-on Scripts

Jan. 2019

Prerequisite (in dock image): (5 mins)

The installation and environment configuration in this section are already included in the docker image we provided. You can skip this section.

- Ubuntu 16.04
- ROS Kinetic desktop full <http://wiki.ros.org/kinetic/Installation/Ubuntu>
- MoveIt <http://moveit.ros.org/install/>

```
sudo apt install ros-kinetic-moveit ros-kinetic-moveit-resources ros-kinetic-moveit-visual-tools  
ros-kinetic-panda-moveit-config ros-kinetic-geometric-shapes ros-kinetic-tf2-geometry-msgs
```

Install necessary debian packages:

```
sudo apt install python-rosinstall python-rosinstall-generator python-wstool  
build-essential
```

```
sudo apt install python-wstool python-catkin-tools clang-format-3.8
```

```
sudo apt install ros-kinetic-universal-robot
```

```
sudo apt install ros-kinetic-ur-description
```

Install handson source code:

```
echo "source /opt/ros/kinetic/setup.bash" >> ~/.bashrc
```

```
mkdir -p ~/ws_handson/src
```

```
cd ~/ws_handson/src
```

```
git clone https://github.com/RoboticsYY/moveit\_handson.git
```

```
git clone https://github.com/RoboticsYY/moveit\_core\_handson.git
```

```
git clone https://github.com/RoboticsYY/moveit\_ros\_handson.git
```

```
cd ..
```

```
catkin_make -DCMAKE_BUILD_TYPE=Release
```

More information:

Onsite technical support: OTC Robotics Engineering Team

Online version of this handson scripts for quick following:

https://roboticsyy.github.io/handson_tutorial/index.html

0. Launch dock image

Some commands need to be run by sudoers on the laptop, the password is: **intel**.

Please follow the command below to install and update docker:

```
sudo apt update && sudo apt install -y wget
```

```
mkdir -p ~/code/ && cd ~/code
```

```
wget
https://raw.githubusercontent.com/RoboticsYY/moveit_handson/master/docker/install_docker.sh
```

```
wget
https://raw.githubusercontent.com/RoboticsYY/moveit_handson/master/docker/setup_docker_display.sh
```

```
chmod +x install_docker.sh
```

```
./install_docker.sh
```

Add your user to the docker group.

```
sudo usermod -aG docker $USER
```

Log out and log back in so that your group membership is re-evaluated. On a desktop Linux environment such as X Windows, log out of your session completely and then log back in.

```
gnome-session-quit
```

If you have a laptop we provided, you can skip this step. If you have a USB stick we provided, the stick contains the handson docker image `moveit_handson_demo.tar.tgz`. Copy the image to the local disk at first, then please follow the description below to decompress and load the image:

```
sudo apt update && sudo apt install -y tar
```

```
tar -zxvf moveit_handson_demo.tar.tgz
```

```
docker load < moveit_handson_demo.tar
```

Please refer below command to verify the docker image created successfully on the disk. Run in shell:

```
docker images
```

It should show the following information:

REPOSITORY	TAG	IMAGE ID	CREATED	SIZE
intel/kinetic	moveit_handson_demo	6643cc4db2e5	5 hours ago	3.47GB

Run following commands in one host terminal to set the operating environment first so that x window can pop up within the docker container:

```
cd ~/code
```

```
chmod +x setup_docker_display.sh
```

```
./setup_docker_display.sh
```

```
docker run -t -i --rm -v /tmp/.X11-unix:/tmp/.X11-unix:rw -v
/tmp/.docker.xauth:/tmp/.docker.xauth:rw -e XAUTHORITY=/tmp/.docker.xauth -e
DISPLAY --name moveit_handson intel/kinetic:moveit_handson_demo bash
```

Note: You should not exit the docker container of this terminal during the whole handson process. Otherwise, your operations in the docker container cannot be saved.

If you want more information on how to use docker, please see the article here for more information: <https://docs.docker.com/install/>

Note: If you don't have a USB stick, you can install the docker image with the following command:

```
docker pull congliu0913/moveit_handson_demo
```

1. Getting Started:

1.1 Setup the handson code: (5 mins)

Run from a second host terminal to load the docker container:

```
docker exec -t -i moveit_handson bash
```

Compile the handson code:

```
catkin_make -DCMAKE_BUILD_TYPE=Release
```


Source the catkin environment:

```
source devel/setup.bash
```

You can check the installation by run:

```
roslaunch handson_description visualize_ur5.launch
```

If everything works fine, you can see the following screen. Then Ctrl-C to exit the roslaunch and finish the check.



2. MoveIt! Configure (30 mins)

MoveIt! config package is used to bring up the MoveIt! motion planning, perception and pick place pipeline. If you have the `ur5_hitbot_ilc_platform_moveit_config` package already git-cloned from the **Getting Started** section, don't change anything in this package. This is the MoveIt! config package we created previously, you can refer to this package when you meet error in the rest of the handson. Next, we will show you how to create the same config package.


2.1 Start MoveIt! Setup Assistant (2 mins)

```
docker exec -t -i moveit_handson bash
```

```
source devel/setup.bash
```


```
roslaunch moveit_setup_assistant setup_assistant.launch
```

The operation flow in this section will be:




2.2 Create new MoveIt! config package (1 mins)

Click on the **Create New MoveIt! Configuration Package** button on the **Start** screen:




2.3 Load urdf file (1 mins)

Click on the **browse** button and navigate to the **ur5_hitbot_with_ilc_platform.urdf.xacro** file in the **handson_description** package. (this file gets installed in **/root/ws_handson/src/moveit_handson/handson_description/urdf/ur5_hitbot_with_ilc_platform.urdf.xacro**) Choose that file and then click **Load Files**. The Setup Assistant will load the files (this might take a few seconds) and present you with this screen:



2.4 Generate self-collision matrix (2 mins)

Click on the **Self-Collisions** pane selector on the left-hand side and click on the **Generate Collision Matrix** button. The Setup Assistant will work for a few seconds before presenting you the results of its computation in the main table:




2.5 Virtual joints (1 mins)


Virtual joints are used primarily to attach the robot to the world. Since the UR5 robot is already attached to the platform and the platform is attached to the world in the loaded urdf file, there is no need to add virtual joints.

2.6 Add arm & hand planning groups (8 mins)


- Click on the **Planning-Groups** panel selector
- Click on **Add Group** button to add arm group:
- We will first add UR5 arm as a planning group:
 - Enter **Group Name** as “ur5_arm”
 - Choose **kdl_kinematics_plugin/KDLKinematicsPlugin** as the kinematics solver.
 - Let **Kin. Search Resolution** and **Kin. Search Timeout** stay at their default values.




- Now, click on the **Add Joints** button:
 - Choose “platform_base_link_joint”, “shoulder_pan_joint”, “shoulder_lift_joint”, “elbow_joint”, “wrist_1_joint”, “wrist_2_joint”, “wrist_3_joint” and “wrist_3_link-tool0_fixed_joint” from the left **Available Joints** list. Add them to the right **Selected Joints** list.
- Click **Save** button to save the selected group:



- Now, the screen should be like this:



- Click **Add Group** button again to add the end-effector group. NOTE that you will do this using a different procedure than adding the arm:
 - Enter **Group Name** as “hand”
 - Let **Kin. Search Resolution** and **Kin. Search Timeout** stay at their default values.



- Click on the **Add Links** button.
- Choose “hitbot_base”, “hitbot_mask”, “hitbot_finger0”, “hitbot_finger0_tip”, “hitbot_finger1” and “hitbot_finger1_tip”, and add them to the list of **Selected Links** on the right hand side.

- Click **Save**

Start

Self-Collisions

Virtual Joints

Planning Groups

Robot Poses

End Effectors

Passive Joints

3D Perception

Simulation

ROS Control

Author Information

Configuration Files

Define Planning Groups

Create and edit 'joint model' groups for your robot based on joint collections, link collections, kinematic chains or subgroups. A planning group defines the set of (joint, link) pairs considered for planning and collision checking. Define individual groups for each subset of the robot you want to plan for. Note: when adding a link to the group, its parent joint is added too and vice versa.

Edit 'hand' Link Collection

	Link Names
34	wrist_3_link
35	ee_link
36	tool0
37	hitbot_base
38	hitbot_finger0
39	hitbot_finger0_tip
40	hitbot_finger1
41	hitbot_finger1_tip
42	hitbot_mask
43	operation_surface


>

<

	Link Names
1	hitbot_base
2	hitbot_finger0
3	hitbot_finger0_tip
4	hitbot_finger1
5	hitbot_finger1_tip
6	hitbot_mask

Save

Cancel



Start

Self-Collisions

Virtual Joints

Planning Groups

Robot Poses

End Effectors

Passive Joints

3D Perception

Simulation

ROS Control

Author Information

Configuration Files

Define Planning Groups

Create and edit 'joint model' groups for your robot based on joint collections, link collections, kinematic chains or subgroups. A planning group defines the set of (joint, link) pairs considered for planning and collision checking. Define individual groups for each subset of the robot you want to plan for. Note: when adding a link to the group, its parent joint is added too and vice versa.

Current Groups

▼ **ur5_arm**

▼ **joints**

platform_base_link_joint - Fixed

shoulder_pan_joint - Revolute

shoulder_lift_joint - Revolute

elbow_joint - Revolute

wrist_1_joint - Revolute

wrist_2_joint - Revolute

wrist_3_joint - Revolute

wrist_3_link-tool0_fixed_joint - Fixed

Links

Chain

Subgroups

▼ **hand**

▼ **joints**

▼ **Links**

hitbot_base

hitbot_finger0

hitbot_finger0_tip

hitbot_finger1

hitbot_finger1_tip

hitbot_mask

Chain


Subgroups

[Expand All](#) [Collapse All](#)


Delete Selected

Edit Selected

Add Group




2.7 Add robot poses (5 mins)



- Click on the **Robot Poses** panel
- Click **Add Pose** button
- Set “home” as **Pose Name**
- Choose “ur5_arm” as **Planning Group**
 - Set “**shoulder_pan_joint**” as “1.57”
 - Set “**shoulder_lift_joint**” as “-1.1738”
 - Set “**elbow_joint**” as “1.5190”
 - Set “**wrist_1_joint**” as “-1.9333”
 - Set “**wrist_2_joint**” as “-1.57”
 - Set “**wrist_3_joint**” as “0.0”
- Click **Save** button to save the pose

2.8 Label end-effectors (5 mins)

- Click on the **End Effectors** panel.
- Click **Add End Effector**.
- Choose “hand” as the **End Effector Name** for the gripper.
- Select “hand” as the **End Effector Group**.
- Select “tool0” as the **Parent Link** for this end-effector.
- Leave **Parent Group** blank.
- Click **Save**.



Note: The screens of **Passive Joints**, **3D Perception**, **Simulation** and **ROS Control** can be skipped, they are not necessary right now.

The passive joints are the unactuated joints of the robot, since UR5 doesn't have such kind of joints, so the **Passive Joints** panel will be skipped.

The **3D Perception** is used to config the parameters of octomap by using a 3D sensor, such as RGBD cameras, stereo cameras or laser scanners. In this hands-on, we will skip this.

The **Simulation** will add necessary tags in the urdf file, so that the physics of the robot will be simulated in Gazebo. Since we have already added these tags manually, so this step can be skipped.


Since the hands-on will be implemented mainly in a simulation environment. You can also skip the **ROS Control** panel, which is used to config the controller parameters for real robot execution.

2.9 Author information (1 mins)

Click on the **Author Information** panel. Enter your name and email address.

2.10 Generate configuration files (1 mins)

- Click on the Configuration Files panel.
- In the **Configuration Package Save Path**, browse to the file location `/root/ws_handson/src/moveit_handson`, and input `handson_moveit_config` as your package name.
- Click on the **Generate Package** button.
- Click **Exit Setup Assistant**. Now, you can find your moveit config package in `/root/ws_handson/src/moveit_handson/handson_moveit_config`.



2.11 Set initial pose to fake_controllers.yaml (1 mins)

Set “home” pose as the initial pose for the simulation:

Open `handson_moveit_config/config/fake_controllers.yaml` with any editor, add the following lines to the end of the file, save and close:

```
initial:
- group: ur5_arm
  pose: home
```

2.12 Adjust moveit.rviz (2 mins)

Open `handson_moveit_config/launch/moveit.rviz`, add `RvizVisualToolsGui` to the subitems of `Panels`, so that it would look like:

Panels:

- Class: rviz/Displays
 - Help Height: 84
 - Name: Displays
 - Property Tree Widget:
 - Expanded: ~
 - Splitter Ratio: 0.742560029
 - Tree Height: 330
- Class: rviz/Help
 - Name: Help
- Class: rviz/Views
 - Expanded:

```
- /Current View1
```

```
Name: Views
```

```
Splitter Ratio: 0.5
```

```
- Class: rviz_visual_tools/RvizVisualToolsGui
```

```
Name: RvizVisualToolsGui
```

```
...
```

Still in the `handson_moveit_config/launch/moveit.rviz` file, add `MarkerArray` to the `Displays` panel, so it would look like:

Visualization Manager:

```
Class: ""
```

```
Displays:
```

```
- Class: rviz/MarkerArray
```

```
Enabled: true
```

```
Marker Topic: /rviz_visual_tools
```

```
Name: MarkerArray
```

```
Namespaces:
```

```
Text: true
```

```
Queue Size: 100
```

```
Value: true
```

```
- Alpha: 0.5
```

```
Cell Size: 1
```

```
Class: rviz/Grid
```

```
Color: 160; 160; 164
```

```
Enabled: true
```

```
Line Style:
```

```
Line Width: 0.03
```

```
Value: Lines
```

```
Name: Grid
```

```
Normal Cell Count: 0
```

```
Offset:
```

```
X: 0
```

```
Y: 0
```

```
Z: 0
```

```
...
```


3. Motion Planning and Execution (10 mins)

Bring up MoveIt! motion planning pipeline in one shell. Remember to source the workspace before executing the command:

```
docker exec -t -i moveit_handson bash
source devel/setup.bash
roslaunch handson_moveit_config demo.launch
```


Note: this command is executed from the config package just created, if you meet error in this section, you can replace the above command by the following command to see the result:

```
roslaunch ur5_hitbot_ilc_platform_moveit_config demo.launch
```

In another shell, run the demo that makes UR5 end-effector to draw letter “X”:

```
docker exec -t -i moveit_handson bash
source devel/setup.bash
roslaunch handson_example draw_x.launch
```

Press the “Next” button on the RvizVisualToolsGui to start the demo



4. Pick and Place (10 mins)

Bring up MoveIt! motion planning pipeline in one shell. Remember to source the workspace before executing the command:

```
docker exec -t -i moveit_handson bash
source devel/setup.bash
roslaunch handson_moveit_config demo.launch
```

Note: this command is executed from the config package just created, if you meet error in this section, you can replace the above command by the following command to see the result:

```
roslaunch ur5_hitbot_ilc_platform_moveit_config demo.launch
```

Run the pick and place demo, in which the UR5 robot will pick a ball with hitbot gripper from the platform surface and place it at another location:

```
docker exec -t -i moveit_handson bash
```

```
source devel/setup.bash
```

```
roslaunch handson_example pick_place.launch
```

